

Managing objects

[Managing system objects](#) / [RICOH ProcessDirector servers](#) / [Starting and stopping servers](#) / Stopping an application server

Stopping an application server

You can stop an application server through the Windows Start menu. Stopping the server prevents RICOH ProcessDirector from accessing any external programs on the Windows system.

To stop an application server:

1. Log in to the Windows system as the user that the application server runs under.
2. Stop the application server. Use the **Stop application server** link in the RICOH ProcessDirector start menu folder.

Parent topic: [Starting and stopping servers](#)